

DENSO Robotics Version Upgrading Information

Notice on Additional and Improved Functions of Controller and Software [October 2022]

Thank you for your continued patronage of the DENSO Robotics products.

Please be informed that the following functions will be improved and added in step with upgrading the RC8A Controller, COBOTTA, and various software versions. We will continue improving our services for our customers, and we wish to ask for your continued patronage.

● Version

RC8A Controller / COBOTTA	Ver. 2.19.0
WINCAPS III	Ver. 3.64.2
VRC	Ver. 2.19.0
RC Vision	Ver. 1.4.8

● Item

[RC8A Controller / COBOTTA]

	Classification	Item
1	New function	Addition of Force Sensor Robust Compliance Control
2	New function	Addition of Asyril EYE Provider

[WINCAPS III]

	Classification	Item
1	New function	Addition of parameters for force sensor-equipped robust compliance function

● Description

[RC8A Controller / COBOTTA]

Item	Outline
Addition of force sensor-equipped robust compliance function	A force sensor-equipped robust compliance function has been made available for use. >Find function details here.
Addition of Asyril EYE Provider	An Asyril EYE Provider has been added to simplify interoperation and configuration of cameras and Asycube (a flexible part feeder).

[WINCAPS III]

Item	Outline
Addition of parameters for force sensor-equipped robust compliance function	Parameters have been added for the force sensor-equipped robust compliance function.